

# Poseidon Trading System (previously known as Currency Messenger System 2)

## INSTALLATION INSTRUCTIONS ON METATRADER 4

In the first section of this user guide, I'm going to describe the installation process of Poseidon Trading System for MetaTrader 4 trading platform build 600 or later.

Our system works on MetaTrader4. You need to install MetaTrader 4 first if you haven't.

Then, follow the steps below to install our indicator:

### **Step 1: Install The Indicators:**

First, you should have already downloaded the ZIP file containing all the installation files from your member area and unzip it into your desktop.


Inside that ZIP file, you'll find several .ex4 indicator files with the extension .ex4

And 1 template file: **mes2system.tpl**

**Next:**

***Open your MT 4 trading platform***


On the menu, Click File --> Open Data Folder



Once you have that data folder open, locate the MQL4 folder inside it.  
Then open that MQL4 folder:

Name ^	Date modified	Type	Size
config	2/7/2014 1:27 PM	File folder	
history	2/7/2014 12:32 PM	File folder	
logs	2/9/2014 12:19 AM	File folder	
<b>MQL4</b>	2/7/2014 12:32 PM	File folder	
profiles	2/7/2014 12:32 PM	File folder	
templates	2/7/2014 12:32 PM	File folder	
tester	2/7/2014 12:32 PM	File folder	
origin.txt	2/7/2014 12:32 PM	Text Document	1 KB

Inside that MQL4 folder, you will see the **Indicators** folder, this is where you need to copy **ALL .ex4** indicator files to.



### Next step:

Once you've opened the Data Folder, locate the **“templates”** folder inside it. Then open that templates folder:

Name	Date modified	Type	Size
config	3/4/2017 9:36 AM	File folder	
history	1/18/2017 7:08 AM	File folder	
logs	4/14/2017 11:09 AM	File folder	
MQL4	1/18/2017 7:06 AM	File folder	
profiles	2/28/2017 8:46 PM	File folder	
templates	4/10/2017 12:45 PM	File folder	
tester	2/14/2017 2:00 PM	File folder	
origin	1/18/2017 7:06 AM	Text Document	1 KB

This templates folder is where you need to copy the template file:  
**mes2system.tpl**

And that's all. You're now ready to run the Poseidon system.

## **RUNNING POSEIDON SYSTEM**

To run The Poseidon System, just start your Meta Trader 4 and load the template: **mes2system.tpl**

In Metatrader 4, click Chart --> Templates --> Load template, and then choose mes2system.tpl

## **USING POSEIDON SYSTEM**

Please watch the videos on the download page to learn how to trade with the Poseidon system.